

**NAME**

`nisplus_table` – Postfix NIS+ client

**SYNOPSIS**

**postmap -q** "*string*" "**nisplus:**[*name=%s*];*name.name*."

**postmap -q -** "**nisplus:**[*name=%s*];*name.name*." <*inputfile*

**DESCRIPTION**

The Postfix mail system uses optional lookup tables. These tables are usually in **dbm** or **db** format. Alternatively, lookup tables can be specified as NIS+ databases.

To find out what types of lookup tables your Postfix system supports use the "**postconf -m**" command.

To test Postfix NIS+ lookup tables, use the "**postmap -q**" command as described in the SYNOPSIS above.

**QUERY SYNTAX**

Most of the NIS+ query is specified via the NIS+ map name. The general format of a Postfix NIS+ map name is as follows:

**nisplus:**[*name=%s*];*name.name.name::column*

Postfix NIS+ map names differ from what one normally would use with commands such as **niscat**:

- With each NIS+ table lookup, "**%s**" is replaced by a version of the lookup string. There can be only one "**%s**" instance in a Postfix NIS+ map name.
- Postfix NIS+ map names use ";" instead of ",", because the latter character is special in the Postfix `main.cf` file. Postfix replaces ";" characters in the map name by "," before making NIS+ queries.
- The "*:column*" part in the NIS+ map name is not part of the actual NIS+ query. Instead, it specifies the number of the table column that provides the lookup result. When no "*:column*" is specified the first column (1) is used.

**EXAMPLE**

A NIS+ aliases map might be queried as follows:

```
alias_maps = dbm:/etc/mail/aliases,
            nisplus:[alias=%s];mail_aliases.org_dir.$mydomain.:1
```

This queries the local aliases file before the NIS+ file.

**SEE ALSO**

`postmap(1)`, Postfix lookup table manager

**README FILES**

Use "**postconf readme\_directory**" or "**postconf html\_directory**" to locate this information.  
**DATABASE\_README**, Postfix lookup table overview

**LICENSE**

The Secure Mailer license must be distributed with this software.

**AUTHOR(S)**

Geoff Gibbs  
 UK-HGMP-RC  
 Hinxton  
 Cambridge  
 CB10 1SB, UK

Adopted and adapted by:  
 Wietse Venema

NISPLUS\_TABLE(5)

NISPLUS\_TABLE(5)

IBM T.J. Watson Research  
P.O. Box 704  
Yorktown Heights, NY 10598, USA